



Three Piece Set for Schools

Design & work: Kokka Fabric

Size:

Lesson Bag (Large size):

about 34cm (l) x about 45cm (w)
about 10cm (d) (excludes handles)

Shoes Case:

about 30cm (l) x about 23cm (w)
x about 6cm (d) (excludes handles)
about 33cm (w) (excludes handles)

Gym Clothes Bag:

about 39cm (l) x about 33cm (w)
(excludes handles)


Materials

- A Fabric: about 110cm wide x 80cm
- B Fabric: about 110cm wide x 100cm
- Fusible Interfacing (medium weight): about 90cm wide x 90cm
- Flat Tape: 25mm wide x 360cm
- Rectangle Buckle: Two pieces (25mm wide)
- Adjustable Slide Buckle: One piece (25mm wide)
- Dot Button: Two pairs (15mm wide)
- Rivet (Large): Four pairs
- Grommet: Two pairs (1cm inner diameter)
- Round Rope (medium size): 300cm

Fabric shown for this sample: LO-41040-1A

Pattern

Unit: cm. []: Seam allowance. Add 1cm seam unless otherwise specified when cutting the fabric.



※ Adhere fusible interfacing on the back of the outer bag fabrics and transition fabrics for the lesson bag and shoes case.


Instructions

1. With the front sides facing each other, sew together the outer bag fabric and transition fabric. Apply stitches

<Lesson Bag and Shoes Case>

With the front sides facing each other, sew together.


Press the seam down to the transition fabric side.




※ Repeat the same process for another set and shoes case.

2. Baste the flat tape to the outer bag fabric

<Lesson Bag>




<Shoes Case>



※ Baste the tape also on the other set.

※ Baste the tape also on the other set.

3. With the front sides facing each other, sew together the bag fabrics at the sides, bottom and gusset



<How to sew the gusset>

Press the seam open.



Sew at 1cm.

※ Repeat the process for the Shoes case.


4. Make the shoulder strap

Put the flat tape (cut to 120cm) through adjustable slide buckle. Fold in three and apply stitches.


Put the other end of the shoulder strap through a rectangle buckle, then put it through the adjustable slide buckle.



5. Baste the shoulder strap on the outer bag fabric of the lesson bag




6. With the front sides facing each other, sew together the outer bag fabric and lining bag fabric at the top opening



※ Repeat the process on the shoes case.


7. Turn it over. Apply stitches around the top opening. Attach a dot button and rivet to finish the lesson bag and shoes case



8. Sew the bag fabrics and transition fabric of the gym clothes bag

With the front sides facing each other, sew together.

Press the seam down to the transition fabric side.




10. Finish the opening. Fold the top opening in three and apply stitches

Apply stitches around the opening.

Fold the top opening in three and apply stitches.

Put the round rope (cut to 150cm - two pieces) through the grommet.



9. Attach the flat tape to the bag fabric. With the front sides facing each other, sew together the bag fabrics at the sides and bottom

