Owls Bag

kokka-fabric.com

The craft projects and works featured in kokka-fabric.com are strictly for personal use and enjoyment.

Please refrain from selling handmade items using the same exact design (including the pieces made in different fabrics) featured in kokka-fabric.com.

Design & work: Kanae Nakayama

Size: 35.5cm (I) 30cm (w-at the top) 12cm (d)


Instructions

Materials

- □ Fabric (Panel, Gusset): 80cm×130cm (Pocket, Handle): 40cm x 110cm wide
- ☐ Fusible guilt batting: 60cm x 80cm
- $\hfill\Box$ Bottom board for the bag: 35cm x 15cm
- □ Snap: 2 pairs (1cm diameter)


Fabric shown for this sample: Lisa Grue JG50300-301(D)

Pattern



Cutting Layout

Numbers in () denote seam allowance. Edges are left cut unless otherwise stated. Edge of the bottom board is left cut.



1. Make the pocket.

3. Make the outer bag.

①With the front sides

facing each other, sew

together the panel and

3 Sew both

sides.

gusset at the bottom.

Panel (front side)

Pocket (front side)

Gusset (reverse side)

2 Cut a slit on the seam of the gusset.

Panel

front side

Pocket

front side

Gusset (reverse side)

①Double fold the pocket opening and sew.


②Attach the fusible quilt batting to the panel outer fabric.

③Baste the pocket to panel outer fabric.

*Make two pieces.

2. Make the gusset.

①Attach the fusible quilt batting to outer fabric. *Make two pieces.



②With the front sides facing each other,

put together the outer fabrics and sew the short side.

4. Make the lining bag.

As in Step 3, repeat the process. (Leave an opening for turning for 18cm on one side.)

5. Make the handles.




①With the front sides facing outside, fold the handle in four and run stitches.

*Make two pieces.

6. Sew together the outer bag and lining bag.

①With the front sides facing each other, sew together the outer and lining bags.




Outer bag

(reverse side)


•

@Baste the handle to the outer bag.



*Attach the handle on the other panel.

• Repeat the process ⊕~③ for the other panel fabric and gusset.



Snap (凸)

Outer bag

(front side)

*Attach the snap on the other gusset at the top.

(4) Insert the bottom board.