1.2m Ready-To-Sew Four Piece Set

Design & Work: Kokka Fabric

Material

□ Outer Fabric   110cm wide × 120cm
□ Lining Fabric   110cm wide × 120cm
□ Fusible interfacing (medium thickness) 110cm wide × 120cm
□ Flat knit zipper One piece (30cm long)

Fabric shown for this sample: P38900-900 (B)

Pattern

All measurements are in centimeters (cm).

Mini Panel Bag Handle
Outer fabric · Fusible interfacing x 2 each

120cm

Panel Bag Handle
Outer fabric · Fusible interfacing x 2 each

Fabric edge

7   32
7   52

Pouch
Outer fabric x 2
Lining fabric x 2
Fusible interfacing x 2
18   32

25
Shoulder Bag
Bag Fabric
Outer fabric   x 2
Lining fabric   x 2
Fusible interfacing x 2
39

Mini Panel
Bag Bag Fabric
Outer fabric x 2
Lining fabric x 2
Fusible interfacing x 2
28   32

Fabric width 110cm

Panel Bag Bag Fabric
Outer fabric x 2
Lining fabric x 2
Fusible interfacing x 2
39   53

6   52

Shoulder Bag Handle
Outer fabric · Fusible interfacing x 1 each

Fabric edge

*Adhere fusible interfacing on the back of the outer fabric.

Instructions

1. Make the handles for panel bag and mini panel bag. Baste the handles to the outer fabric.

2.5cm
Handle (front side)
Fold for 1cm
0.2cm wide stitch
*Make two pieces each for both panel bag and mini bag.

Baste the handle at 0.5cm
6.5cm 6.5cm
Center
Panel bag outer fabric (front side)

Baste the handle at 0.5cm
6cm 6cm
Center
Mini panel bag outer fabric (front side)

2. With the front sides facing each other, sew together the bag fabrics at the sides and bottom.

Sew at 1cm
Panel bag outer fabric (reverse side)

Sew at 1cm
Panel bag lining fabric (reverse side)
Leave an opening for turning (about 12cm)

*Repeat the same process for Mini panel bag.

3. With the front sides facing each other, sew together the outer bag fabric and lining bag fabric at the top opening. Turn it inside out, stitch around the opening to finish the panel bag.

Panel bag lining fabric (front side)
Sew the top opening at 1cm.
Panel bag outer fabric (reverse side)
Turn it inside out.

0.2cm wide stitch
Panel bag outer fabric (front side)
*Close the opening for turning.

*Repeat the same process for Mini panel bag.

4. Make the shoulder bag handle.

2cm
Handle (front side)
Fold for 1cm
0.2cm wide stitch

5. With the front sides facing each other, sew together the shoulder bag outer fabrics at the sides and the bottom.

Sew at 1cm
Shoulder bag outer fabric (reverse side)

Sew at 1cm
Shoulder bag outer fabric (reverse side)
Leave an opening for turning (about 12cm)

6. With the front sides facing each other, sew together the outer bag fabric and lining bag fabric at the top opening. Turn it inside out, titch around the opening to finish the shoulder bag!

Align the bag fabric's stitch line and the center of the handle.
Baste the handle
Shoulder bag lining fabric (front side)
Sew the top opening at 1cm.
Shoulder bag outer fabric (reverse side)
Handle
Lining fabric (front side)
*Baste the other side as shown.
Turn it inside out.

0.2cm wide stitch
Shoulder bag outer fabric (front side)
*Close the opening for turning.

7. Attach the zipper to the outer fabric of the pouch.

Zipper (front side)
Pouch outer fabric (reverse side)
Sew at 0.7cm

0.2cm wide stitch
Pouch outer fabric (front side)

With the front sides facing each other, sew together the outer fabric and zipper at 0.7cm from the edge.

8. With the front sides facing each other, sew together the pouch fabrics at the sides and bottom.

Pouch outer fabric (reverse side)
Sew at 1cm

Pouch lining fabric (reverse side)
Fold the top opening of the lining fabric for 0.7cm.
Sew at 1cm

9. To finish the pouch, sew the top opening of the lining fabric onto the zipper using blind stitches.

Pouch lining fabric (front side)
Sew the top opening of the lining fabric onto the zipper using blind stitches.

Pouch outer fabric (front side)
Turn it inside out to finish.